



Release note – MultiOne Workflow 3.13

In this release the following items were changed (compared to the previous version):

CHANGES

- Added:
 - Support for new (versions of) LED devices

name	12nc
TrustSight DALI 45-300V NiMH IDT	929002145906
Xitanium 20W/a 0.15-0.5A 54V CD 3CB 230V	929002107106
Xitanium 20W/a 0.15-0.5A 54V CD 3CW 230V	929002107306
Xitanium 20W/m 0.15-0.5A 54V CD 230V	929002106906
Xitanium 36W/a 0.3-1.05A 54V CD 3CB 230V	929002107206
Xitanium 36W/a 0.3-1.05A 54V CD 3CW 230V	929002107406
Xitanium 36W/m 0.3-1.05A 54V CD 230V	929002107006
Xitanium 35W 0.08-0.35A 220V S16 230V	929002115806
Xitanium 60W 0.08-0.35A 300V S16 230V	929002115906
Xitanium 60W 0.15-0.5A 220V S16 230V	929002116006
Xitanium 100W 0.25-0.7A 220V S21 230V	929002116106
XH180C090V285BSF2	929001783013

XH180C125V200BSF2	929001783113
XH180C180V144BSF2	929001783213
XI180C090V285BSF2	929001782713
XI180C125V200BSF2	929001782813
XI180C180V144BSF2	929001782913
XI040C110V054PST2	929001780613
XI050C140V054PST2	929001780713

- New Features:
 - Added feature Tx Power for EasyAir
 - Added test procedure according FCC-Red for EasyAir
 - Support DALI: part 252 Energy Meter
 - Support DALI: part 253 Diagnostics
- Updated features
 - Relax feature compatibility between single active level and dual active level Lineswitch.
 - “Override” Dynadimmer is moved to “Dimming Interface”.
 - Firmware list updated to available drivers.
 - DALI: part 251.
 - By flagging “Dynamic Date” the luminaire info configuration date can be made dynamic. When enabled, the date (year and week) of the PC will be configured into the driver, by MultiOne Workflow/CommandLine.
 - The user has the opportunity by flagging “Use device ID” to use the unique number of the device as luminaire identification.
- Improved functionality
 - Support for latest FEIG LCN9620 and LCN9630 software versions.

IMPORTANT NOTICE

Make sure that also the extra conditions are fulfilled:

- User Software Key on line or off line installed (no action needed if PC already has a key)
- Put the *Power mode* of your PC settings in *best performance*.
- The correct Microsoft Windows version,
 - o No Windows XP support
 - o When running the installer on Windows 10, a 'Do not run' button might be shown as the application is not signed. Go to 'more info' to force installation.

The MultiOne software is tested on a wide variety of virus scanners (latest versions), no issues detected.



Document: 29-10-2019
No: RNW3 2019v0
Author: E.Bos